



USB Driver Update to version DR 6.1.00.B


The following information shows the way to update the old infrared thermometer adapter driver for thermoMETER sensors by the new, digitally signed version DR 6.1.00.B. Please follow the steps below:




1. Open the device manager and go to „driver update...“.




2. Select: „No, not this time“.




3. Select: „Install from a list or specific location“.




4. Select: „Select driver by yourself“.




5. Select: „Infrared Sensor Adapter Com Port“ and go to Next.



6. Select: „IR Company“ and go to Next.



7. Click on Finish.



8. If you now look into your device manager the correct new driver (DR 6.1.00.B) should show up.